Configuring Web Server

Prerequisites:

- Install VMWare Tools through Player -> Manage -> Install VMWare Tools
- Configure IE ESC by setting it "Off" for administrators

Security Information			🗑 Go to Windows Fire
Windows Firewall:	Public: On		Configure Updates
Last checked for updates:	Never		Run Security Config
h Internet Explorer Enhanced Se	curity Configuration	×	
Internet Explorer Enhanced Securi exposure of your server to potent	ity Configuration (IE ESC) reduces t tial attacks from Web-based content	he t.	
Internet Explorer Enhanced Securi default for Administrators and Use	ity Configuration is enabled by ers groups.		
Administrators:			
O n (Recommended)			
🔇 💿 off			
Users:			
On (Recommended)			
🔇 C off			
More about Internet Explorer Enh	anced Security Configuration		
	ОК Са	ancel	

Go to the following site on your "host" computer (the real computer):

- <u>ftp://10.6.2.38</u>
- Username: admin
- Password: "No Password"
- Download and drag the following installation files into the virtual machine
 - o Chrome
 - o Office
 - Microsoft Security Essentials

Configure IP settings:

- Click on your network adapter, then "Open Network and Sharing Center"
- Click on "Change adapter settings"
- Right click on Local Area Connection and select Properties



- Configure your IP settings to match the rest of your network: 192.168."Your two numbers".3
 - This example uses 151 as the 3rd number,
 DON'T use it, use your 3rd number!!!!

Local Area Connection Properties Networking Connect using:		iecuuri "
Intel(R) PRO/1000 MT Network Conn	Internet Protocol Version 4 (TCP/IP)	v4) Properties
This connection uses the following items:	General You can get IP settings assigned autor this capability. Otherwise, you need to for the appropriate IP settings. © Obtain an IP address automatica © Use the following IP address: IP address: Subnet mask:	natically if your network supports o ask your network administrator lly
Install [[pinetal]	Default gateway:	192 . 168 . 151 . 1
Description Transmission Control Protocol/Internet Pro wide area network protocol that provides r	C Obtain DNS server address autor	natically fresses:
across diverse interconnected networks.	Preferred DNS server:	192.168.151.2
	Validate settings upon exit	Advanced
		OK Cancel

Installing IIS role:

Go to the Server Manager and click on "Add Roles"



Click next



• Select "Web Server (IIS)

Add Roles Wizard		X
Select Server Ro	les	
Before You Begin Server Roles Web Server (IIS) Role Services Confirmation Progress Results	Select one or more roles to install on this server. Roles: Active Directory Certificate Services Active Directory Domain Services Active Directory Pederation Services Active Directory Rights Management Services Application Server DHCP Server Fax Server File Services Hyper-V Network Policy and Access Services Print and Document Services Wholows Deployment Services Windows Server Update Services Windows Server Update Services More about server roles	Description: Web Server (IIS) provides a reliable, manageable, and scalable Web application infrastructure. application infrastructure.

Click next



• Click next



• Click Install



Click Finish



Done